

# SIDRA INTERSECTION 5.1 Command Line Parameters and Registry Settings for "SILENT" Installation

13 Sep 2011

The SIDRA INTERSECTION 5.1 installation package "SIDRAINTERSECTION51Setup.exe" (full version) or "SIDRAINTERSECTION51Update.exe" (update version) natively supports standard Windows Installer command-line parameters.

A commonly requested scenario for command-line parameters is for IT System Administrators to perform a "Silent" installation of SIDRA INTERSECTION 5.1 such that no UI is present. However, this approach requires a method of passing particular installation parameters on the command-line which are usually captured within the installation UI to set up such things as the Default Model, and licensing-related parameters.

## Example Silent Installation command line:

```
SIDRAINTERSECTION51Setup /qn DEFAULT_MODEL_SIGNATURE={Model Signature}  
LICENSING_METHOD={LicensingMethod} FLOATING_LICENSE_FOLDER={FloatingLicenseFolder}  
CUSTOM_LICENSE_FILE={CustomLicenseFile} UPDATE_ENABLED={UpdateEnabled}
```

Note: All command-line parameters are OPTIONAL, if any are not specified default values will be used.

## DEFAULT\_MODEL\_SIGNATURE={Model Signature}

Where {Model Signature} is one of the following:

Model	{Model Signature}
Standard Left:	1bfd96bf-b305-4cde-b782-6a8bbc475eaa
Standard Right:	b914db43-8c0a-47bc-8451-617909607c4e
New Zealand:	7b6c560c-cadd-411a-92cf-34599217c0c3
US HCM (Metric):	8b0b3015-f8f3-44d3-9d57-cd0e806774f0
US HCM (US):	746c8c58-a34f-415b-8570-7dfa3c1dfb1e
RTA NSW:	364d52db-3427-4548-85e2-7c9f5bf44240

Default value: *empty string*, "Standard Left" will be used at runtime

## Example:

```
DEFAULT_MODEL_SIGNATURE=1bfd96bf-b305-4cde-b782-6a8bbc475eaa
```

## LICENSING\_METHOD={LicensingMethod}

{LicensingMethod} defines the licensing method SI5.1 will use:

Method	{LicensingMethod}
Fixed	0
Floating	1
Custom	2

Default value: *empty string*, "Fixed" will be used at runtime

Example:

```
LICENSING_METHOD=1
```

## FLOATING\_LICENSE\_FOLDER={FloatingLicenseFolder}

{FloatingLicenseFolder} is a FOLDER/PATH where the floating license file is located. This path may also be given as a UNC path.

Default value: *empty string*

Example:

```
FLOATING_LICENSE_FOLDER=\\server\folder
FLOATING_LICENSE_FOLDER=L:\folder
```

## CUSTOM\_LICENSE\_FILE={CustomLicenseFile}

{CustomLicenseFile} is a full path to a pre-existing license file. We recommend that the custom license file be copied to one of the following locations:

- **Vista and Windows 7:** "C:\ProgramData\SIDRA SOLUTIONS\Licenses\"
- **Windows XP:** "C:\Documents and Settings\All Users\Application Data\SIDRA SOLUTIONS\Licenses\"

Quotes are required if the path contains spaces.

Default value: *empty string*

Example:

```
CUSTOM_LICENSE_FILE="C:\ProgramData\SIDRA SOLUTIONS\Licenses\licensefile.lf"
```

## UPDATE\_ENABLED={UpdateEnabled}

{UpdateEnabled} enables or disables the Automatic Update function and removes the "Check for Updates" button in the software if updates are disabled:

	{UpdateEnabled}
False	0
True	1

Default value: 1

Example:

```
UPDATE_ENABLED=0
```

## SAMPLES

Silent install setting custom model, floating license method, floating license folder and disabling update functions:

```
SIDRAINTERSECTION51Setup /qn DEFAULT_MODEL_SIGNATURE=364d52db-3427-4548-85e2-7c9f5bf44240 LICENSING_METHOD=1 FLOATING_LICENSE_FOLDER=L:\folder UPDATE_ENABLED=0
```

Silent install setting custom model, custom license method, custom license file and disabling update functions:

```
SIDRAINTERSECTION51Setup /qn DEFAULT_MODEL_SIGNATURE=364d52db-3427-4548-85e2-7c9f5bf44240 LICENSING_METHOD=2 CUSTOM_LICENSE_FILE="C:\ProgramData\SIDRA SOLUTIONS\Licenses\licensefile.lf" UPDATE_ENABLED=0
```

## REGISTRY SETTINGS

If it is not feasible to set these parameters via the installation command line, they can be set directly in the registry. Registry entries corresponding to the above settings can be found under registry key:

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\SIDRA SOLUTIONS\SIDRA INTERSECTION 5.1]  
(64-bit systems), or
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\SIDRA SOLUTIONS\SIDRA INTERSECTION 5.1] (32-bit systems)
```

The relevant Strings are:

```
"CustomLicenseFile"=""  
"FloatingLicenseFolder"=""  
"LicensingMethod"=""  
"ModelSignature"=""  
"UpdateEnabled"=""
```

The String values are as described above for command line settings.